

1、 HD camera calibration

1、 HD camera calibration

1.1、 Preparation before calibration

1.2、 Calibration

Wiki: http://wiki.ros.org/camera_calibration

HD camera: https://github.com/bosch-ros-pkg/usb_cam.git

HD camera tutorials: http://wiki.ros.org/camera_calibration/Tutorials/MonocularCalibration

1.1、 Preparation before calibration


- You need a [checkerboard](#). This tutorial uses a 9x6 checkerboard and a 20mm square, which should be flattened during calibration.

The calibration uses the internal vertex of the checkerboard, so the "10x7" checkerboard uses the internal vertex parameter "9x6", as shown in the example below.

The calibration board of any specification can be used, just change the parameters.

- An open area without obstacles and calibration board patterns
- Monocular camera that publishes images via ROS

Checkerboard (calibration board)



7×10 | Size: 20mm

1.2、Calibration

Start up Astra camera

```
roslaunch uvc_camera uvc_camera_node device:=/dev/video0
```

View picture topic

```
yahboom@Yahboom:~$ rostopic list
/camera_info
/image_raw
/image_raw/compressed
/image_raw/compressed/parameter_descriptions
/image_raw/compressed/parameter_updates
/image_raw/compressedDepth
/image_raw/compressedDepth/parameter_descriptions
/image_raw/compressedDepth/parameter_updates
/image_raw/theora
/image_raw/theora/parameter_descriptions
/image_raw/theora/parameter_updates
/rosout
/rosout_agg
```


Start the calibration node

```
roslaunch camera_calibration cameracalibrator.py image:=/image_raw camera:=/ --size
9x6 --square 0.02
```

size: The number of internal corners of the calibrated checkerboard, such as 9X6, the corners have six rows and nine columns.

square: The side length of the checkerboard, in meters.

image and camera: Set the topic of the image released by the camera.



Calibration interface


X: The left and right movement of the checkerboard in the camera field of view

Y: The checkerboard moves up and down in the camera's field of view


Size: the back and forth movement of the checkerboard in the camera's field of view

Skew: The tilt and rotation of the checkerboard in the camera field of view

After the startup is successful, put the checkerboard into the center of the screen and change different poses. The system will recognize it autonomously. In the best case, the lines under [X], [Y], [Size], and [Skew] will first change from red to yellow and then to green as the data is collected, filling them as much as possible.



Click [CALIBRATE] to calculate the camera internal parameters, the more pictures, the longer the time, just wait.



Click [SAVE] to save the uncalibrated result, the bottom line appears, click [COMMIT] to exit.。

```

**** Calibrating ****
*** Added sample 46, p_x = 0.760, p_y = 0.692, p_size = 0.601, skew = 0.209
D = [0.15472379170842887, -0.8099148429709959, 0.001638104297210457, -0.004547715577735416, 0.0]
K = [908.7489797733236, 0.0, 206.95349685217326, 0.0, 909.6731941878273, 301.76750022317515, 0.0, 0.0, 1.0]
R = [1.0, 0.0, 0.0, 0.0, 1.0, 0.0, 0.0, 0.0, 1.0]
P = [903.021484375, 0.0, 203.24846800838714, 0.0, 0.0, 916.7886962890625, 302.28809574724073, 0.0, 0.0, 0.0, 1.0, 0.0]
None
# oST version 5.0 parameters

[image]

width
640

height
480

[narrow_stereo]

camera matrix
908.748980 0.000000 206.953497
0.000000 909.673194 301.767500
0.000000 0.000000 1.000000

distortion
0.154724 -0.809915 0.001638 -0.004548 0.000000

rectification
1.000000 0.000000 0.000000
0.000000 1.000000 0.000000
0.000000 0.000000 1.000000

projection
903.021484 0.000000 203.248468 0.000000
0.000000 916.788696 302.288096 0.000000
0.000000 0.000000 1.000000 0.000000

('Wrote calibration data to', '/tmp/calibrationdata.tar.gz')

```

After the calibration, the calibration result is stored in [/tmp/calibrationdata.tar.gz], you can move it out to see the content

```
sudo mv /tmp/calibrationdata.tar.gz ~
```

After decompression, there are the image just calibrated, an ost.txt file and an ost.yaml file. The yaml file is what we need, but it needs to be modified before it can be used.

- Change ost.yaml to head_camera.yaml
- Change the name of camera_name: to head_camera
- Move the file to ~/.ros/camera_info folder